Issue a Free SSL Certificate on HestiaCP — Step by Step 2026

HestiaCP · https://www.hyyat.com/en/knowledgebase/free-ssl-hestiacp/

In short To issue SSL on HestiaCP: from the WEB section click Edit next to the domain, enable SSL Support, Let's Encrypt Support and auto-renew, then Save. Your site is on https and the certificate auto-renews.

Embedded media: https://www.hyyat.com/wp-content/uploads/2026/11/hyyat-cp-hest-ssl-en.mp4?_=1

Securing your site with an **SSL** certificate puts it on **https**, protects visitor data and improves your search rankings. **HestiaCP** issues a free Let's Encrypt certificate in a few clicks. In this guide from the Hyyat Host team we show the steps.

Hyyat Host virtual servers with NVMe storage, full control and Arabic support are a solid base for your secured sites.

Explore Hyyat Host VPS plans ←

Before you start you need a created site and a domain pointing to your server — see creating a website on HestiaCP.

Steps to issue the certificate

1. **Open the domain settings** From the `WEB` section click `Edit` next to your site.
2. **Enable SSL support** Turn on `SSL Support`.

3. **Enable Let's Encrypt** Turn on `Let's Encrypt Support` to issue a free certificate automatically, and enable auto-renew if shown.
4. **Enable https redirect** Turn on `Enable automatic HTTPS redirection` to send visitors to https automatically.
5. **Save** Click `Save` and wait a few seconds for the certificate to be issued.

The Let's Encrypt certificate auto-renews before it expires, so no periodic action is needed. You can also secure the HestiaCP panel itself with a certificate from the server settings.

Common issues and fixes

- **Issuance fails:** most often the domain doesn't point to your server IP — fix the A record in DNS, wait for propagation and retry.
- **Site shows «not secure» after issuing:** make sure automatic https redirection is enabled.
- **Mixed content:** update image and file links inside your site to https.

Related guides

- Install WordPress on HestiaCP.
- Backups and restore on HestiaCP.
- Securing the HestiaCP panel.

Next step

- Make sure automatic https redirection is enabled.
- Enable recurring backups.
- See the VPS control panel comparison to learn each panel's strengths.

And if you'd like us to secure your site for you, open a support ticket — we reply within 24 hours at most.

Frequently asked questions

How do I issue SSL on HestiaCP?

From the WEB section click Edit next to the domain, enable SSL Support and Let's Encrypt Support then Save.

Is the certificate free?

Yes, Let's Encrypt certificates are completely free and auto-renew.

Does the certificate renew automatically?

Yes, it renews before expiry without any action from you.

Need this service from Hyyat Host?Our team handles it for you, with support replying to tickets within 24 hours at most.

Web HostingSaudi Hosting